

## Bitdefender GravityZone **Advanced** Business Security

GravityZone Advanced Business Security [產品說明](#), [產品型錄](#), [功能比較表](#)

支援 Windows Desktop / Server, Mac, Linux，實體機、虛擬機的安全防護控管：

- **GravityZone Business Security** (支援 Client + File Server)
- **GravityZone Advanced Business Security** (支援 Client + File Server + Exchange Server)。如使用 **On-premise Console** 還能支援 Mobile devices 行動裝置: Apple iPhones and iPad tablets (iOS 5.1+), Google Android smartphones and tablets (2.2+)

下列提供 Bitdefender 企業版產品相關說明，有二點注意事項敬請留意：

1. 企業版產品為全英文介面，序號只能在台灣註冊授權使用。
2. 因為每個客戶端的軟硬體環境不同，請務必先測試安裝產品試用，確認規格及功能符合需求。如有需要申請產品測試請跟我說，試用過程如有任何問題都會協助您排除。

### GravityZone - Introduction (功能介紹影片):

[http://www.bitdefender.qcomgroup.com.tw/download/Bitdefender GravityZone news.swf](http://www.bitdefender.qcomgroup.com.tw/download/Bitdefender_GravityZone_news.swf)

※可以直接用 IE 瀏覽器開啟播放，不需要另外安裝 Player (如要安裝 Player 可以使用 [SWF File Player](#)).

### 產品系統需求：

#### Supported Endpoint Operating Systems:

- Windows 10, Windows 8, 8.1, Windows 7, Windows Vista (SP1), Windows XP (SP3)
- Mac OS High Sierra (10.13.x), Mac OS Sierra (10.12.x), OS X El Capitan (10.11.x), OS X Yosemite (10.10.5), OS X Mavericks (10.9.5), OS X Mountain Lion (10.8.5)
- Linux: Red Hat Ent. 6.2, 6.1, 5.7, 5.6; CentOS 6.2, 6.1, 5.7, 5.6; Ubuntu 11.04, 10.04; SUSE Ent. Server 11; OpenSUSE 12, 11; Fedora 16, 15
- Windows Embedded 8 Standard, Windows Embedded 8.1 Industry, Windows Embedded Standard 7, Windows Embedded POSReady 7, Windows Embedded Enterprise 7, Windows Embedded POSReady 2009, Windows Embedded Standard 2009, Windows XP Embedded with Service Pack 2, Windows XP Tablet PC Edition

- Windows Server 2016, Windows Server 2016 Core, Windows Server 2012, Windows Server 2012 R2, Windows Small Business Server (SBS) 2011, Windows Small Business Server (SBS) 2008, Windows Server 2008 R2, Windows Server 2008, Windows Small Business Server (SBS) 2003, Windows Server 2003 R2, Windows Server 2003 with Service Pack 1, Windows Home Server

#### **Endpoint hardware requirements:**

- Minimum : 2.4 GHz single-core CPU  
Recommended: 1.86 GHz or faster Intel Xeon multi-core CPU
- Memory:  
Minimum free RAM: 512 MB  
Recommended free RAM: 1 GB  
HDD space: 1.5 GB of free hard-disk space

#### **Supported mobile devices:**

- Apple iPhones and iPad tablets (iOS 5.1+)
- Google Android smartphones and tablets (2.2+)

#### **GravityZone Control Center (on-premise console)**

- GravityZone Control Center is delivered as a virtual appliance and is available in the following formats:
- OVA (compatible with VMware vSphere, View)
- XVA (compatible with Citrix XenServer, XenDesktop, VDI-in-a-Box)
- VHD (compatible with Microsoft Hyper-V)
- Support for other formats and virtualization platforms may be provided on request.

#### **Control Center Minimum Hardware Requirements**

- CPU: 4 vCPU with 2 GHz each
- Minimum RAM memory: 6 GB recommended
- 40 GB of free hard-disk space
- Internet access for updates and communication with remote and mobile endpoints.

#### **Supported email servers:**

- Exchange 2013, 2010, 2007;
- Exchange 2013, 2010, 2007;
- Roles: Edge, Hub and Mailbox;
- Protocols: SMTP, MAPI, Exchange ActiveSync;

產品安裝說明：

**Using the Cloud Console option 雲端控制台** (security infrastructure hosted and maintained by Bitdefender) ※由 Bitdefender 託管和維護的安全基礎架構。

- **Advantages:**

- Web console is instantly available and does not require technical skills to manage
- Zero costs with servers and maintenance
- Real-time control and monitoring of offsite and remote users without VPN

- **Console Installation:**

- 1. Log in to [gravityzone.bitdefender.com](https://gravityzone.bitdefender.com) with the credentials you received by email.
- 2. Start installing Bitdefender protection on your computers using the download link, or mass deployment options.
- 3. Monitor or change protection settings efficiently using the remote web console. Download the [Installation Guide](#) for detailed installation instructions.

**Using the On-premise Console 本地控制台** ※將 GravityZone Virtual Appliance 映像檔掛載在虛擬機上，此 Virtual Appliance 即為 On-premise Console Server。

- **Advantages:**

- More control over the security console.

- **Console Installation:**

- 1. Download the virtual appliance that corresponds to your environment. The download link will be provided by your reseller or delivered to you by mail after signing up for the free 30 -day trial.

- 2. Load the virtual appliance into the hypervisor and proceed through the configuration steps.
- 3. Access the console address in your browser and start to deploy endpoints.
- 4. Monitor or change protection settings efficiently using the remote web console. Download the [Installation Guide](#) for detailed installation instructions.

產品安裝手冊：

<b>CLOUD CONSOLE</b>	<b>ON-PREMISE CONSOLE</b>	
<a href="#"><u>Installation Guide</u></a>	<a href="#"><u>Installation Guide</u></a>	The guide offers essential information to help you deploy GravityZone in your local network.
<a href="#"><u>Installation Guide (AWS)</u></a>	-	This guide explains how to deploy GravityZone in an Amazon EC2 network environment.
<a href="#"><u>Administrator's Guide</u></a>	<a href="#"><u>Administrator's Guide</u></a>	The guide helps you manage and monitor the security of your local network with GravityZone.
<a href="#"><u>Administrator's Guide (AWS)</u></a>	-	This guide explains how to manage and monitor network security with GravityZone in an Amazon EC2 environment.
<a href="#"><u>Reporter's Guide</u></a>	<a href="#"><u>Reporter's Guide</u></a>	This guide shows how you can monitor the security of your network with GravityZone.
<a href="#"><u>Reporter's Guide (AWS)</u></a>	-	This guide helps you monitor network security with GravityZone, when integrated with Amazon EC2.
<a href="#"><u>Bitdefender Endpoint Security Tools Users Guide</u></a>		This guide is intended to help Windows users run local scans and remove malware from their systems.
<a href="#"><u>Endpoint Security for MAC Users Guide</u></a>		This guide is intended to help Mac users run local scans and remove malware from their systems.
<a href="#"><u>API Documentation</u></a>	<a href="#"><u>API Documentation</u></a>	The guide helps developers automate business workflows using the Bitdefender GravityZone APIs.